

997 Functional Acknowledgment

X12/V4060/997: 997 Functional Acknowledgment

Version: 6.06

Table of Contents

997 Functional Acknowledgment	1
ISA Interchange Control Header	3
GS Functional Group Header	6
ST Transaction Set Header	8
AK1 Functional Group Response Header	9
AK2 Loop AK2	10
AK2 Transaction Set Response Header	11
AK5 Transaction Set Response Trailer	12
AK9 Functional Group Response Trailer	13
SE Transaction Set Trailer	14
GE Functional Group Trailer	15
IEA Interchange Control Trailer	16

997 Functional Acknowledgment

Functional Group=FA

This X12 Transaction Set contains the format and establishes the data contents of the Functional Acknowledgment Transaction Set (997) for use within the context of an Electronic Data Interchange (EDI) environment. The transaction set can be used to define the control structures for a set of acknowledgments to indicate the results of the syntactical analysis of the electronically encoded documents. The encoded documents are the transaction sets, which are grouped in functional groups, used in defining transactions for business data interchange. This standard does not cover the semantic meaning of the information encoded in the transaction sets.

Not Defined:

<u>Pos</u>	<u>Id</u>	<u>Segment Name</u>	<u>Req</u>	<u>Max Use</u>	<u>Repeat</u>	<u>Notes</u>	<u>Usage</u>
	ISA	Interchange Control Header	M	1			Must use
	GS	Functional Group Header	M	1			Must use

Heading:

<u>Pos</u>	<u>Id</u>	<u>Segment Name</u>	<u>Req</u>	<u>Max Use</u>	<u>Repeat</u>	<u>Notes</u>	<u>Usage</u>
0100	ST	Transaction Set Header	M	1		N1/0100	Must use
0200	AK1	Functional Group Response Header	M	1		N1/0200	Must use

<u>LOOP ID - AK2</u>			<u>999999</u>	<u>N1/0300L</u>	
0300	AK2	Transaction Set Response Header	M	1	N1/0300 Must use
0600	AK5	Transaction Set Response Trailer	M	1	Must use
0700	AK9	Functional Group Response Trailer	M	1	Must use
0800	SE	Transaction Set Trailer	M	1	Must use

Not Defined:

<u>Pos</u>	<u>Id</u>	<u>Segment Name</u>	<u>Req</u>	<u>Max Use</u>	<u>Repeat</u>	<u>Notes</u>	<u>Usage</u>
	GE	Functional Group Trailer	M	1			Must use
	IEA	Interchange Control Trailer	M	1			Must use

Notes:

- 1/0100 These acknowledgments shall not be acknowledged, thereby preventing an endless cycle of acknowledgments of acknowledgments. Nor shall a Functional Acknowledgment be sent to report errors in a previous Functional Acknowledgment.
The Functional Group Header Segment (GS) is used to start the envelope for the Functional Acknowledgment Transaction Sets. In preparing the functional group of acknowledgments, the application sender's code and the application receiver's code, taken from the functional group being acknowledged, are exchanged; therefore, one acknowledgment functional group responds to only those functional groups from one application receiver's code to one application sender's code.
There is only one Functional Acknowledgment Transaction Set per acknowledged functional group.
- 1/0200 AK1 is used to respond to the functional group header and to start the acknowledgment for a functional group. There shall be one AK1 segment for the functional group that is being acknowledged.
The Functional Acknowledgement is generated at the point of translation, intended for the originator (not any intermediate parties).
- 1/0300L AK2 is used to start the acknowledgment of a transaction set within the received functional group. The AK2 segments shall appear in the same order as the transaction sets in the functional group that has been received and is being acknowledged.

1/0300 AK2 is used to start the acknowledgment of a transaction set within the received functional group. The AK2 segments shall appear in the same order as the transaction sets in the functional group that has been received and is being acknowledged.

yISA Interchange Control Header

Pos:	Max: 1
Not Defined - Mandatory	
Loop: N/A	Elements: 16

User Option (Usage): Must use

To start and identify an interchange of zero or more functional groups and interchange-related control segments

Element Summary:

<u>Ref</u>	<u>Id</u>	<u>Element Name</u>	<u>Req</u>	<u>Type</u>	<u>Min/Max</u>	<u>Usage</u>
ISA01	I01	Authorization Information Qualifier	M	ID	2/2	Must use
		Description: Code identifying the type of information in the Authorization Information				
		Code Name				
		00 No Authorization Information Present (No Meaningful Information in I02)				
ISA02	I02	Authorization Information	M	AN	10/10	Must use
		Description: Information used for additional identification or authorization of the interchange sender or the data in the interchange; the type of information is set by the Authorization Information Qualifier (I01)				
ISA03	I03	Security Information Qualifier	M	ID	2/2	Must use
		Description: Code identifying the type of information in the Security Information				
		Code Name				
		00 No Security Information Present (No Meaningful Information in I04)				
ISA04	I04	Security Information	M	AN	10/10	Must use
		Description: This is used for identifying the security information about the interchange sender or the data in the interchange; the type of information is set by the Security Information Qualifier (I03)				
ISA05	I05	Interchange ID Qualifier	M	ID	2/2	Must use
		Description: Code indicating the system/method of code structure used to designate the sender or receiver ID element being qualified				
		All valid standard codes are used.				
ISA06	I06	Interchange Sender ID	M	AN	15/15	Must use
		Description: Identification code published by the sender for other parties to use as the receiver ID to route data to them; the sender always codes this value in the sender ID element				
ISA07	I05	Interchange ID Qualifier	M	ID	2/2	Must use

<u>Ref</u>	<u>Id</u>	<u>Element Name</u>	<u>Req</u>	<u>Type</u>	<u>Min/Max</u>	<u>Usage</u>
		<p>Description: Code indicating the system/method of code structure used to designate the sender or receiver ID element being qualified</p> <p>All valid standard codes are used.</p>				
ISA08	I07	<p>Interchange Receiver ID</p> <p>Description: Identification code published by the receiver of the data; When sending, it is used by the sender as their sending ID, thus other parties sending to them will use this as a receiving ID to route data to them</p>	M	AN	15/15	Must use
ISA09	I08	<p>Interchange Date</p> <p>Description: Date of the interchange</p>	M	DT	6/6	Must use
ISA10	I09	<p>Interchange Time</p> <p>Description: Time of the interchange</p>	M	TM	4/4	Must use
ISA11	I65	<p>Repetition Separator</p> <p>Description: Type is not applicable; the repetition separator is a delimiter and not a data element; this field provides the delimiter used to separate repeated occurrences of a simple data element or a composite data structure; this value must be different than the data element separator, component element separator, and the segment terminator</p> <p>Code Name</p> <p>! Exclamation Point</p> <p>:</p> <p>@ At</p> <p>] Bracket</p> <p>^ Carrot</p> <p> Pipe</p> <p>HD Supply Requirements:</p> <p><i>This separator can be any non-alpha-numeric character that is also not used as an element separator, segment terminator or elsewhere in the data.</i></p>	M		1/1	Must use
ISA12	I11	<p>Interchange Control Version Number</p> <p>Description: Code specifying the version number of the interchange control segments</p> <p>Code Name</p> <p>00406 Standards Approved for Publication by ASC X12 Procedures Review Board through October 2002</p>	M	ID	5/5	Must use
ISA13	I12	<p>Interchange Control Number</p> <p>Description: A control number assigned by the interchange sender</p>	M	N0	9/9	Must use
ISA14	I13	<p>Acknowledgment Requested</p>	M	ID	1/1	Must use

<u>Ref</u>	<u>Id</u>	<u>Element Name</u>	<u>Req</u>	<u>Type</u>	<u>Min/Max</u>	<u>Usage</u>
		<p>Description: Code indicating sender's request for an interchange acknowledgment</p> <p>Code Name</p> <p>0 No Interchange Acknowledgment Requested</p>				
ISA15	I14	Interchange Usage Indicator	M	ID	1/1	Must use
		<p>Description: Code indicating whether data enclosed by this interchange envelope is test, production or information</p> <p>Code Name</p> <p>P Production Data</p>				
ISA16	I15	Component Element Separator	M		1/1	Must use
		<p>Description: Type is not applicable; the component element separator is a delimiter and not a data element; this field provides the delimiter used to separate component data elements within a composite data structure; this value must be different than the data element separator and the segment terminator</p>				

GS Functional Group Header

Pos:	Max: 1
Not Defined - Mandatory	
Loop: N/A	Elements: 8

User Option (Usage): Must use

To indicate the beginning of a functional group and to provide control information

Element Summary:

<u>Ref</u>	<u>Id</u>	<u>Element Name</u>	<u>Req</u>	<u>Type</u>	<u>Min/Max</u>	<u>Usage</u>
GS01	479	Functional Identifier Code	M	ID	2/2	Must use
		Description: Code identifying a group of application related transaction sets				
		Code Name				
		FA Functional Acknowledgment (997)				
GS02	142	Application Sender's Code	M	AN	2/15	Must use
		Description: Code identifying party sending transmission; codes agreed to by trading partners				
GS03	124	Application Receiver's Code	M	AN	2/15	Must use
		Description: Code identifying party receiving transmission; codes agreed to by trading partners				
GS04	373	Date	M	DT	8/8	Must use
		Description: Date expressed as CCYYMMDD where CC represents the first two digits of the calendar year				
GS05	337	Time	M	TM	4/8	Must use
		Description: Time expressed in 24-hour clock time as follows: HHMM, or HHMMSS, or HHMMSSD, or HHMMSSDD, where H = hours (00-23), M = minutes (00-59), S = integer seconds (00-59) and DD = decimal seconds; decimal seconds are expressed as follows: D = tenths (0-9) and DD = hundredths (00-99)				
GS06	28	Group Control Number	M	N0	1/9	Must use
		Description: Assigned number originated and maintained by the sender				
GS07	455	Responsible Agency Code	M	ID	1/2	Must use
		Description: Code identifying the issuer of the standard; this code is used in conjunction with Data Element 480				
		Code Name				
		X Accredited Standards Committee X12				

GS08	480	Version / Release / Industry Identifier Code	M	AN	1/12	Must use
------	-----	---	---	----	------	----------

Description: Code indicating the version, release, subrelease, and industry identifier of the EDI standard being used, including the GS and GE segments; if code in DE455 in GS segment is X, then in DE 480 positions 1-3 are the version number; positions 4-6 are the release and subrelease, level of the version; and positions 7-12 are the industry or trade association identifiers (optionally assigned by user); if code in DE455 in GS segment is T, then other formats are allowed

Code Name

004060 Standards Approved for Publication by ASC X12 Procedures Review Board through October 2002

Semantics:

1. GS04 is the group date.
2. GS05 is the group time.
3. The data interchange control number GS06 in this header must be identical to the same data element in the associated functional group trailer, GE02.

Comments:

1. A functional group of related transaction sets, within the scope of X12 standards, consists of a collection of similar transaction sets enclosed by a functional group header and a functional group trailer.

ST Transaction Set Header

Pos: 0100	Max: 1
Heading - Mandatory	
Loop: N/A	Elements: 2

User Option (Usage): Must use

To indicate the start of a transaction set and to assign a control number

Element Summary:

<u>Ref</u>	<u>Id</u>	<u>Element Name</u>	<u>Req</u>	<u>Type</u>	<u>Min/Max</u>	<u>Usage</u>
ST01	143	Transaction Set Identifier Code	M	ID	3/3	Must use
		Description: Code uniquely identifying a Transaction Set				
		Code Name				
		997 Functional Acknowledgment				
ST02	329	Transaction Set Control Number	M	AN	4/9	Must use
		Description: Identifying control number that must be unique within the transaction set functional group assigned by the originator for a transaction set				

Semantics:

1. The transaction set identifier (ST01) is used by the translation routines of the interchange partners to select the appropriate transaction set definition (e.g., 810 selects the Invoice Transaction Set).

AK1 Functional Group Response Header

Pos: 0200	Max: 1
Heading - Mandatory	
Loop: N/A	Elements: 2

User Option (Usage): Must use

To start acknowledgment of a functional group

Element Summary:

<u>Ref</u>	<u>Id</u>	<u>Element Name</u>	<u>Req</u>	<u>Type</u>	<u>Min/Max</u>	<u>Usage</u>
AK101	479	Functional Identifier Code	M	ID	2/2	Must use
<p>Description: Code identifying a group of application related transaction sets</p> <p>HD Supply Requirements: <i>Your GS01 2-digit code from the original document being acknowledged.</i></p> <p>All valid standard codes are used.</p>						
AK102	28	Group Control Number	M	NO	1/9	Must use
<p>Description: Assigned number originated and maintained by the sender</p> <p>HD Supply Requirements: <i>Your Group Control Number from the original document being acknowledged.</i></p>						

Semantics:

1. AK101 is the functional ID found in the GS segment (GS01) in the functional group being acknowledged.
2. AK102 is the functional group control number found in the GS segment in the functional group being acknowledged.

Loop AK2

Pos: 0300	Repeat: 999999
Mandatory	
Loop: AK2	Elements: N/A

User Option (Usage): Must use

To start acknowledgment of a single transaction set

Loop Summary:

<u>Pos</u>	<u>Id</u>	<u>Segment Name</u>	<u>Req</u>	<u>Max Use</u>	<u>Repeat</u>	<u>Usage</u>
0300	AK2	Transaction Set Response Header	M	1		Must use
0600	AK5	Transaction Set Response Trailer	M	1		Must use

AK2 Transaction Set Response Header

Pos: 0300	Max: 1
Heading - Mandatory	
Loop: AK2	Elements: 2

User Option (Usage): Must use

To start acknowledgment of a single transaction set

Element Summary:

<u>Ref</u>	<u>Id</u>	<u>Element Name</u>	<u>Req</u>	<u>Type</u>	<u>Min/Max</u>	<u>Usage</u>
AK201	143	Transaction Set Identifier Code	M	ID	3/3	Must use
		<p>Description: Code uniquely identifying a Transaction Set</p> <p>HD Supply Requirements: <i>Your ST01 document code from the original document being acknowledged.</i></p> <p>All valid standard codes are used.</p>				
AK202	329	Transaction Set Control Number	M	AN	4/9	Must use
		<p>Description: Identifying control number that must be unique within the transaction set functional group assigned by the originator for a transaction set</p> <p>HD Supply Requirements: <i>Your Transaction Set control number from the original document being acknowledged.</i></p>				

Semantics:

1. AK201 is the transaction set ID found in the ST segment (ST01) in the transaction set being acknowledged.
2. AK202 is the transaction set control number found in the ST segment in the transaction set being acknowledged.

AK5 Transaction Set Response Trailer

Pos: 0600	Max: 1
Heading - Mandatory	
Loop: AK2	Elements: 1

User Option (Usage): Must use

To acknowledge acceptance or rejection and report errors in a transaction set

Element Summary:

<u>Ref</u>	<u>Id</u>	<u>Element Name</u>	<u>Req</u>	<u>Type</u>	<u>Min/Max</u>	<u>Usage</u>
AK501	717	Transaction Set Acknowledgment Code	M	ID	1/1	Must use

Description: Code indicating accept or reject condition based on the syntax editing of the transaction set

Code Name

- A Accepted
- E Accepted But Errors Were Noted
- R Rejected

AK9 Functional Group Response Trailer

Pos: 0700	Max: 1
Heading - Mandatory	
Loop: N/A	Elements: 4

User Option (Usage): Must use

To acknowledge acceptance or rejection of a functional group and report the number of included transaction sets from the original trailer, the accepted sets, and the received sets in this functional group

Element Summary:

<u>Ref</u>	<u>Id</u>	<u>Element Name</u>	<u>Req</u>	<u>Type</u>	<u>Min/Max</u>	<u>Usage</u>
AK901	715	Functional Group Acknowledge Code	M	ID	1/1	Must use
<p>Description: Code indicating accept or reject condition based on the syntax editing of the functional group</p> <p>HD Supply Requirements: <i>If "A" (accepted), then the group was accepted with no ANSI X12 errors. If "R" or "E", this means that a document in this group has an error.</i></p> <p>Code Name</p> <p>A Accepted E Accepted, But Errors Were Noted. P Partially Accepted, At Least One Transaction Set Was Rejected R Rejected</p>						
AK902	97	Number of Transaction Sets Included	M	N0	1/6	Must use
<p>Description: Total number of transaction sets included in the functional group or interchange (transmission) group terminated by the trailer containing this data element</p> <p>HD Supply Requirements: <i>Number of Transaction Sets (documents) included in the Group. Should equal the number of AK2/AK5 sets in this 997.</i></p>						
AK903	123	Number of Received Transaction Sets	M	N0	1/6	Must use
<p>Description: Number of Transaction Sets received</p>						
AK904	2	Number of Accepted Transaction Sets	M	N0	1/6	Must use
<p>Description: Number of accepted Transaction Sets in a Functional Group</p>						

Comments:

1. If AK901 contains the value "A" or "E", then the transmitted functional group is accepted.

SE Transaction Set Trailer

Pos: 0800	Max: 1
Heading - Mandatory	
Loop: N/A	Elements: 2

User Option (Usage): Must use

To indicate the end of the transaction set and provide the count of the transmitted segments (including the beginning (ST) and ending (SE) segments)

Element Summary:

<u>Ref</u>	<u>Id</u>	<u>Element Name</u>	<u>Req</u>	<u>Type</u>	<u>Min/Max</u>	<u>Usage</u>
SE01	96	Number of Included Segments	M	NO	1/10	Must use
		Description: Total number of segments included in a transaction set including ST and SE segments				
SE02	329	Transaction Set Control Number	M	AN	4/9	Must use
		Description: Identifying control number that must be unique within the transaction set functional group assigned by the originator for a transaction set				

Comments:

1. SE is the last segment of each transaction set.

GE Functional Group Trailer

Pos:	Max: 1
Not Defined - Mandatory	
Loop: N/A	Elements: 2

User Option (Usage): Must use

To indicate the end of a functional group and to provide control information

Element Summary:

<u>Ref</u>	<u>Id</u>	<u>Element Name</u>	<u>Req</u>	<u>Type</u>	<u>Min/Max</u>	<u>Usage</u>
GE01	97	Number of Transaction Sets Included	M	NO	1/6	Must use
		Description: Total number of transaction sets included in the functional group or interchange (transmission) group terminated by the trailer containing this data element				
GE02	28	Group Control Number	M	NO	1/9	Must use
		Description: Assigned number originated and maintained by the sender				

Semantics:

1. The data interchange control number GE02 in this trailer must be identical to the same data element in the associated functional group header, GS06.

Comments:

1. The use of identical data interchange control numbers in the associated functional group header and trailer is designed to maximize functional group integrity. The control number is the same as that used in the corresponding header.

IEA Interchange Control Trailer

Pos:	Max: 1
Not Defined - Mandatory	
Loop: N/A	Elements: 2

User Option (Usage): Must use

To define the end of an interchange of zero or more functional groups and interchange-related control segments

Element Summary:

<u>Ref</u>	<u>Id</u>	<u>Element Name</u>	<u>Req</u>	<u>Type</u>	<u>Min/Max</u>	<u>Usage</u>
IEA01	I16	Number of Included Functional Groups	M	N0	1/5	Must use
		Description: A count of the number of functional groups included in an interchange				
IEA02	I12	Interchange Control Number	M	N0	9/9	Must use
		Description: A control number assigned by the interchange sender				